X2E C++ API Guide



COPYRIGHT

This manual is copyright © 2015, PhaseSpace, Inc., All Rights Reserved. This document may not, in whole or in part, be copied, photocopied, reproduced, translated, or reduced to electronic medium or machine-readable form without prior consent, in writing, from PhaseSpace, Inc.

The distribution and sale of this product are intended for the use of the original purchaser only. Duplicating, selling, or otherwise distributing this product is a violation of the law.

DISCLAIMER

PHASESPACE INC. MAKES NO WARRANTIES, EITHER EXPRESSED OR IMPLIED, WITH RESPECT TO THE SYSTEM DESCRIBED HEREIN, ITS QUALITY, PERFORMANCE, MERCHANTABILITY OR FITNESS FOR ANY PARTICULAR PURPOSE. THIS SYSTEM IS SOLD "AS IS". THE ENTIRE RISK AS TO ITS PERFORMANCE IS WITH THE BUYER. SHOULD THE SYSTEM PROVE DEFECTIVE FOLLOWING ITS PURCHASE, THE BUYER (AND NOT PHASESPACE, INC. THEIR DISTRIBUTORS OR THEIR RETAILERS) ASSUMES THE ENTIRE COST OF ALL NECESSARY DAMAGES. IN NO EVENT WILL PHASESPACE, INC. BE LIABLE FOR DIRECT, INDIRECT, INCIDENTAL OR CONSEQUENTIAL DAMAGES RESULTING FROM NOT ALLOW THE SYSTEM EVEN IF IT HAS BEEN ADVISED OF THE POSSIBILITY OF SUCH DAMAGES. SOME LAWS DO NOT ALLOW THE EXCLUSION OR LIMITATION OF IMPLIED WARRANTIES OR LIABILITIES FOR INCIDENTAL OR CONSEQUENTIAL DAMAGES, SO THE ABOVE LIMITATION OR EXCLUSION MAY NOT APPLY.

PhaseSpace and the PhaseSpace logo are registered trademarks, and all PhaseSpace product names are trademarks of PhaseSpace Inc.

Common Conventions

- id is an unsigned 32-bit integer (-1 is invalid) representing the marker's ID
- time is an unsigned 64-bit integer (-1 is invalid) representing the time when data was acquired in frames (for libowlsock, time is different for other libowl/owlserver implementations)
- pose is the position [x, y, z] and quaternion rotation [s, x, y, z]
- options
 - Options are represented by key-value pairs: key=value
 - Multiple pairs are separated by spaces: key1=value1 key2=value2 ...
 - Multiple values belonging to one key are separated by commas: key=value1, value2, value3,...

Data Structures

Tracker Data Structures

```
uint32 t id;
Camera
          uint32 t flags;
          float pose[7];
          float
                    cond;
          uint32 t id;
  Peak
          uint32 t flags;
              • 0x0001 = LED too high/low
              • 0x0010 = Predicted

    0x0100 = Amplitude too low

    0x0200 = Amplitude too high

              • 0x0400 = 3D distance rejected

    0x0800 = Unidentified pattern

               0x1000 = Internal
          int64 t time;
          uint16 t camera;
          uint16 t detector;
          uint32 t width;
          float
                    pos;
          float
                    amp;
Plane
          uint32 t id;
          uint32 t flags;

    0x0001 = LED too high/low

              • 0x0010 = Predicted

    0x0100 = Amplitude too low
```

```
    0x0200 = Amplitude too high

              • 0x0400 = 3D distance rejected
              • 0x0800 = Unidentified pattern
              • 0x1000 = Internal
          int64 t time;
          uint16 t camera;
          uint16 t detector;
          float plane[4];
          float
                  cond;
          uint32 t id;
Marker
          uint32 t flags;
             • 0x000F = Slot number
                0 \times 0010 = Predicted
             • 0x0100 = 3D rejected
          int64 t time;
          float
                    x, y, z;
          float
                     cond;

    Condition number of plane intersection matrix

             · Low positive numbers are good condition values, negative
                numbers are not
 Rigid
          uint32 t id;
          uint32 t flags;

    Mask 0x4 = Kalman estimate

          int64 t time;
                   pose[7];
          float
          float
                    cond;

    Number of constraint planes

    Higher positive numbers are good condition values, negative

                numbers are not
          uint64 t hw id;
 Input
          uint64 t flags;
          int64 t time;
          std::vector<uint8 t> data;

    Arbitrary data transport

                Associated with DeviceInfo by hw id
```

Typedef Declarations for Tracker Structures

```
std::vector<Camera> Cameras;
std::vector<Peak> Peaks;
std::vector<Plane> Planes;
std::vector<Marker> Markers;
std::vector<Rigid> Rigids;
std::vector<Input> Inputs;
```

Information Data Structures

```
MarkerInfo
               uint32 t
                             id;
                uint32 t
                            tracker id;
                std::string name;
                std::string options;
TrackerInfo
                uint32 t
                             id;
                std::string type;
                Type can be point or rigid
                std::string name;
                std::string options;
                std::vector<uint32 t> marker ids;
FilterInfo
                uint32 t
                            period;
                std::string name;
                std::string options;
                • Options key-value pairs: Type=value

    Multiple filter types supported

                 • Filter Types:
                   o noop - No operation
                  • linear - Linear interpolation
                   • spline - Cubic hermite spline interpolation
                   • average - Averaging interpolation
                uint32 t
                             hw id;
 DeviceInfo

    Unique hardware identifier

                uint32 t
                             id;

    Unique identifier within same type

                std::string name;
                std::string options;
                std::string status;
                int64 t
                           time;
                std::string type;
                • Device type: none, hub, camera, stylus, puck, controller
```

Polymorphic Data Structures

Туре	 Polymorphic data structure accessor Converts data and type identifier to type (const T*) or (T) Type operators: template <typename t=""> operator const T*()</typename> const; Return value: Pointer to value converted to T on success 0 on error template <typename t=""> operator T() const;</typename> Return value:
	Value converted to □ on success

	Value of T() on error
Variant	 Stores one or more values of a single type Data accessors: uint16_t type_id() const; uint32_t flags() const; const char* type_name() const; bool valid() const; bool empty() const; const Type begin() const; const Type end() const; template <typename t=""> size_t get(T &v) const;</typename> T is STL compatible container Fill container v with values Return value: Number of elements in v on success 0 on error std::string str() const; Recomended for string types Return value: value converted to string on success empty string on error Operators (can also be used to access data): Variant& operator=(const Variant &v); template <typename t=""> operator T() const;</typename> Return value: Value converted to T on success Value of T() on error template <typename t=""> operator std::vector<t>() const;</t></typename> Return value: std::vector<t>() const;</t> Return value: std::vector<t> containing value(s) on success</t>
Event	 Empty std::vector<t> on error</t> Named polymorphic data structure Primary data transport from OWL server to OWL client Can contain child Events Data accessors: begin() and end() iterators uint16_t type_id() const; uint16_t id() const; uint32_t flags() const; int64_t time() const; const char* type_name() const;

```
o const char* name() const;
o template <typename T> size t size() const;
  Return value:

    Number of elements of type T on success

    0 on error

o template <typename T> size t get(T &v) const;
   ■ T is STL compatible container
  ■ Fill v with values
   Return value:

    Number of elements in v on success

     • 0 on error
o std::string str() const;
  Return value:

    Value converted to string on success

    Empty string on error

o const Event* find(uint16 t type id, const
     std::string &name) const;
   ■ Find self or child event of either type id or name
   Return value:
     • const Event pointer to self or child Event on success

    0 on error
```

Context Class

Functions & Accessors

```
int open (
      const std::string &name,
      const std::string &open options=std::string()

    Opens connection to name

                                       · Return value:

    Blocks until success/failure or

                                         > 0 on success
  timeout expired
                                         o 0 on timeout

    Clears properties

                                         o < 0 on error (lastError is set)</pre>
 • Sets properties: name, opened
 • open options:
   timeout (in ysec, default 5s)
bool close()
 • Calls done () and closes

    Return value: success or failure

   connection
bool isOpen() const

    Return value: connection open or closed

int initialize(
```

```
const std::string &init_options
```

- Initializes opened connection
- Blocks until success/failure or timeout expired
- Clears properties
- Sets properties: initializing, initialized
- Multiple connections are handled master/slave(s)
 - Single master connection is allowed
 - First connection defaults to master (slave=0)
 - Subsequent connectsion are slave (slave=1)
 - First connection can be forced to be slave with slave=1, will wait for master connection until timeout
- init options:
 - timeout (in ysec, default 5s)
 - o slave
 - o profile
 - o event
 - o streaming
 - o frequency
 - timebase (numerator, denominator)
 - o scale
 - o pose (7 values)

- Return value:
 - > 0 on success (Creates Event BYTE initialized)
 - o 0 on timeout
 - o < 0 on error (Sets lastError)</pre>

```
int done(
     const std::string &done_options=std::string()
)
```

- Un-initializes initialized connection
- Blocks until all remaining events are received or timeout expires
- Sets properties: flushing, initialized, streaming, frequency
- done options:
 - timeout (in usec, default 1s)

- Return value:
 - > 0 on success (Creates Event BYTE done)
 - 0 on timeout = 0
 - o < 0 on failure (Sets lastError)</pre>

int streaming() const

	Return value: stream enabled/disabled		
<pre>bool streaming(int enable)</pre>			
 Enables/disables streaming Valid parameters: 1: Streaming over TCP 2: Streaming over UDP 3: Streaming over UDP broadcast 	Return value: success/failure (Upon success, creates Event INT streaming)		
<pre>float frequency() const</pre>			
	Return value: stream frequency		
<pre>bool frequency(float freq)</pre>			
Sets stream frequency	Return value: success/failure (Upon success, creates Event FLOAT frequency)		
<pre>const int* timeBase() const</pre>			
	 Return value: Pointer to timebase pair on success 0 on error 		
<pre>bool timeBase(int num, int den)</pre>			
Set timebase numerator and denominator	 Return value: success/failure (Upon success, creates Event INT timebase) 		
float scale() const			
	Return value: scale factor		
<pre>bool scale(float scale)</pre>			
Set scale factor	Return value: success/failure (Upon success, creates Event FLOAT scale)		
<pre>const float* pose() const</pre>			
	Return value:Pointer to pose (7 values)0 on error		

```
bool pose (
     const float *pose

    Set pose (7 values)

                                      • Return value: success/failure (Upon success,
                                        creates Event FLOAT scale)
std::string option(
      const std::string &option
) const

    Return value:

                                        o Option's value on success

    Empty string on error

std::string options() const

    Return value:

    All options, separated by spaces

    Empty string on error

bool option (
      const std::string &option,
      const std::string &value
                                      · Return value: success/failure

    Sets option to value

bool options (
      const std::string &options
                                      · Return value: success/failure

    Sets options separated by space

std::string lastError() const

    Return value: last error, or empty string

bool markerName(
      uint32 t marker id,
      const std::string marker name

    Set name of marker

                                      · Return value: success/failure
bool markerOptions(
      uint32 t marker id,
      const std::string &marker_options

    For markers in rigid body tracker:

    Return value: success/failure

   ∘ pos=vector (x, y, z) rigid
```

```
body coordinates
const MarkerInfo markerInfo(
      uint32 t marker id
) const

    Return value: MarkerInfo of marker with given ID

bool createTracker(
     uint32 t tracker id,
     const std::string &tracker type,
     const std::string &tracker name = std::string(),
      const std::string &tracker options = std::string()

    Create a tracker

    Return value: success/failure

bool createTrackers(
     const TrackerInfo *first,
     const TrackerInfo *last

    Create multiple trackers

    Return value: success/failure

bool destroyTracker(
     uint32 t tracker id

    Remove a tracker

    Return value: success/failure

bool destroyTrackers(
     const uint32 t *first,
     const uint32 t *last

    Remove multiple trackers

    Return value: success/failure

bool assignMarker(
     uint32 t tracker id,
     uint32 t marker id,
     const std::string &marker name = std::string(),
      const std::string &marker options = std::string()

    Assign marker to tracker

    Return value: success/failure

    Removes marker from previous

  tracker
bool assignMarkers(
     const MarkerInfo *first,
     const MarkerInfo *last
```

```
    Assign markers to tracker

    Return value: success/failure

bool trackerName(
      uint32 t tracker id,
      const std::string &tracker name

    Set name of tracker

    Return value: success/failure

bool trackerOptions(
      uint32 t tracker id,
      const std::string &tracker options

    Set tracker options

    Return value: success/failure

    For rigid body tracker:

   o init=value (4 numbers)
   ∘ default init=1e-3, 1, 0.5,
const TrackerInfo trackerInfo(
      uint32 t tracker id
) const

    Return value: TrackerInfo of tracker with given

bool filter(
      uint32 t period,
      const std::string &name,
      const std::string &filter options
 · Create filter

    Return value: success/failure

bool filters(
     const FilterInfo *first,
      const FilterInfo *last
 · Create multiple filters

    Return value: success/failure

const FilterInfo filterInfo(
     const std::string &name
) const

    Return value: FilterInfo of filter with given name

const DeviceInfo deviceInfo(
     uint64 t hw id
) const

    Return value: DeviceInfo of device with given

                                       hardware ID
const Event* peekEvent(
```

```
long timeout = 0
);

    Look at next event without removing
    Return value: Pointer to next Event

  it from the event queue
const Event* nextEvent(
     long timeout = 0
);
• Get next event, removes it from the

    Return value: Pointer to next Event

  event queue
const Variant property(
     const std::string &name
) const

    Property types:

    Return value:

    Read-only property value on success

   Integers

    Empty/invalid Variant on error

        opened
        initializing
        ■ initialized
        ■ slave
        streaming
        systemtimebase
        ■ timebase
        markers
        trackers
   Floats
        maxfrequency
        systemfrequency
        frequency
        ■ scale
        systempose
        pose
   String
        name
        ■ profile
        ■ filters
        profiles
        ■ defaultprofile
        ■ profiles.json
   Camera
```

Scan Class

Scan for OWL servers (owld)

```
bool send(
     const std::string &message
);

    Send message to all OWL servers

    Return value: success/failure

   on local network
std::vector<std::string> listen(
      long timeout = 0
);

    Receive messages from one or

    Return value:

   more OWL servers after timeout
                                       o std::vector<std::string> containing
 • Value: ip=address (message from
                                          OWL server messages on success
   server)
                                       o Empty std::vector<std::string> on
                                          error or timeout
```